## Instructions to Quick Access ComTrader

In order to connect to M7 Trading PROD OPCOM you must access the following address in your web browser <a href="https://portal.m7.energy/xrpm/">https://portal.m7.energy/xrpm/</a> (See picture below)

E HT Energy - OPCOM C $\times$ + $\vee$		-	
$\leftarrow$ $\rightarrow$ O $\textcircled{a}$ $\textcircled{https://portal.m7.energy/x}$	rpm/ 🔲 📩	te ll	r
ע opcom ₪			Â
M7 Com Welcome to the M7 Trading ComTrader laun ComTrader WebStart & St	ch page. Below you will	find the links fi	or
Standalone	WebStar	t Client	
Full performance version Requires: 6GB memory / 64bit OS	Lower performa Requires: Java WebSta		y *
Download	Star	rt	
DEL GRC	JTSCHE BÖRSE JUP		



In this page you have two options to start the application. In the first one you can run a Standalone version.



Click **Download.** You will be prompted by a pop-up to save the archive to your Computer.



Figure 2

After that you need to extract the archive. Right-Click on the file and select "Extract All...", then select the folder destination as shown below:

	×
Extract Compressed (Zipped) Folders	
Select a Destination and Extract Files	
Files will be extracted to this folder:	
C:\comtrader-static-6.9.57-XRPM-prod Browse	
⊡ Show extracted files when complete	
Extract Cano	el



Access the **comtrader-static-6.9.57-XRPM-prod** folder and double click **ComTrader-6.9.57-6G-XRPM-prod.exe** (Figure 4).

NOTE: The file with 4G in the name needs at least 6GB of RAM.

The file with 6G in the name needs at least 8GB of RAM.

Name	Date modified	Туре	Size
📙 jre	20-Aug-20 8:45 AM	File folder	
ScomTrader-6.9.57-4G-XRPM-prod	20-Aug-20 8:45 AM	Application	48,850 KB
∑ ComTrader-6.9.57-6G-XRPM-prod	20-Aug-20 8:45 AM	Application	48,850 KB

## Figure 4

## For ComTrader to run smoothly, you should also allow access to:

Servers prod1.profiles.m7.deutsche-boerse.com and prod2.profiles.m7.deutsche-boerse.com on port 60000

and

Servers prod1.opcom.m7.deutsche-boerse.com and prod2.opcom.m7.deutsche-boerse.com on port 50080.

After Comtrader was launched, you must fill the empty boxes with User and Password provided by OPCOM.

If you are behind a proxy you must click on the Connection tab located in bottom left of the window and enter your proxy details. (See picture below)

ComTrader 6.9.57	– 🗆 X
General Profile Help	
Exchange Login	$\mathbf{Y}$
Enter user id and password to connect to exchange.	opcom
Enter user la and password to connect to exchange.	production
User	Ð Login
user id	
	🕩 Logout
Password	
Password	Forgotten password
T domoid	
No Proxy	
Host Port User Name	Password
IP address or hostname Port User Name	Password
Safeguards Connection	

Figure 5

Reports are generated for report user who belongs to the market participant (member).

All trading related activities are documented in XML reports which are generated based on data of the M7 Trading PROD OPCOM and can be downloaded via the WebGUI accesible with reporting user credentials at:

https://prod1.opcom.m7.deutsche-boerse.com:60080 or https://prod2.opcom.m7.deutsche-boerse.com:60080

## 2. The second option is to run the ComTrader via Web.

WebStart Client
Lower performance version es: Java WebStart / 1GB memory *
Start

Click Start (! in this scenario you must have at least version Java 8.60 !)

You will be prompted by a pop-up to save the java file to your Computer.

What do you want to do with ComTrader.jnlp (1.1 KB)? From: portal.m7.energy	Open	Save	^	Cancel	×

Figure 6

Click **Open** and wait. In the new windows click **Run**.




Figure 7

The Comtrader is launched.

ComTrader 6.9.57	– 🗆 X
General Profile Help	
Exchange Login Enter user id and password to connect to exchange.	production
User	➡ Login
	🕩 Logout
Password Password	Forgotten password
CONFIDENTIAL	
Action in case of disconnection:	
No Action	
Deactivate orders on trader level	
Deactivate orders on account level	
Safeguards Connection	

Figure 8

You must fill the empty boxes with User and Password provided by OPCOM.

If you are behind a proxy you must click on the Connection tab located in bottom left of the window and enter your proxy details. (See picture below)

ComTrader 6.9.57	—
General Profile Help	
Exchange Login	X
Enter user id and password to connect to exchange.	opcom production
User	➡ Login
user id	🕞 Logout
Password	
Password	Forgotten password
(HTTP Proxy	
Host Port	User Name Password
(IP address or hostname Port	User Name
Safeguards Connection	

Figure 9